

# AVAILABLE TRUNKS



Admin

Applications

Connectivity

Dashboard

Reports

Settings

UCP

## Trunks

This page is used to manage various system trunks

+ Add Trunk ▾

Name	Tech	CallerID	Status
Sarevoz_in	sip	940000007	Enabled
Sarevoz_out	sip	940000007	Enabled

# GENERAL INBOUND TRUNK

[Admin](#)[Applications](#)[Connectivity](#)[Dashboard](#)[Reports](#)[Settings](#)[UCP](#)

## Edit Trunk

**WARNING: This trunk is not used by any routes!**

This trunk will not be able to be used for outbound calls until a route is setup that uses it.

Click on [Outbound Routes](#) to setup routing.

[General](#)[Dialed Number Manipulation Rules](#)[sip Settings](#)**Trunk Name** ⓘ**Hide CallerID** ⓘ**Outbound CallerID** ⓘ**CID Options** ⓘ**Maximum Channels** ⓘ**Asterisk Trunk Dial Options** ⓘ**Continue if Busy** ⓘ**Disable Trunk** ⓘ

# SIP SETTINGS INBOUND TRUNK

[Admin](#)[Applications](#)[Connectivity](#)[Dashboard](#)[Reports](#)[Settings](#)[UCP](#)

## Edit Trunk

**WARNING: This trunk is not used by any routes!**

This trunk will not be able to be used for outbound calls until a route is setup that uses it.

Click on [Outbound Routes](#) to setup routing.

[General](#)[Dialed Number Manipulation Rules](#)[sip Settings](#)[Outgoing](#)[Incoming](#)**Trunk Name** ⓘ**PEER Details** ⓘ

```
host=194.30.6.32
username='suegraenruso'
secret=estorba
fromuser='suegraenruso'
fromdomain=194.30.6.32
sendrpid=no
type=peer
insecure=invite
directmedia=no
```

# REGISTER STRING INBOUND TRUNK



Admin

Applications

Connectivity

Dashboard

Reports

Settings

UCP

## Edit Trunk

**WARNING: This trunk is not used by any routes!**

This trunk will not be able to be used for outbound calls until a route is setup that uses it.  
Click on [Outbound Routes](#) to setup routing.

General

Dialed Number Manipulation Rules

sip Settings

Outgoing

Incoming

USER Context ?

suegraenruso

USER Details ?

Register String ?

suegraenruso:estorba @194.30.6.32

# GENERAL OUTBOUND TRUNK

[Admin](#)[Applications](#)[Connectivity](#)[Dashboard](#)[Reports](#)[Settings](#)[UCP](#)

## Edit Trunk

In use by 1 route

[General](#)[Dialed Number Manipulation Rules](#)[sip Settings](#)**Trunk Name** [?](#)**Hide CallerID** [?](#) Yes  No**Outbound CallerID** [?](#)**CID Options** [?](#) Allow Any CID Block Foreign CIDs Remove CNAM Force Trunk CID**Maximum Channels** [?](#)**Asterisk Trunk Dial Options** [?](#) Override System**Continue if Busy** [?](#) Yes  No**Disable Trunk** [?](#) Yes  No

# SIP SETTINGS OUTBOUND TRUNK



Admin

Applications

Connectivity

Dashboard

Reports

Settings

UCP

## Edit Trunk

In use by 1 route

General

Dialed Number Manipulation Rules

**sip Settings**

**Outgoing**

Incoming

**Trunk Name** ?

Sarevoz\_out

**PEER Details** ?

```
host=194.30.6.32
username=suegraenruso
secret=estorba
fromuser=suegraenruso
fromdomain=194.30.6.32
sendrpid=pai
type=peer
context=from-trunk-sip-Sarevoz_out
directmedia=no
```

# NO REGISTER CONFIG. IN OUTBOUND TRUNK

## Edit Trunk

In use by 1 route

**USER Context** [?](#)

**USER Details** [?](#)

**Register String** [?](#)

# AVAILABLE OUTBOUND ROUTES



Admin

Applications

Connectivity

Dashboard

Reports





Settings

UCP

## Outbound Routes

This page is used to manage your outbound routing.

+ Add Outbound Route

Name	Outbound CID	Attributes
+ sarevoz_out_trunk		   



# OUTBOUND ROUTE CONFIGURATION



Admin

Applications

Connectivity

Dashboard

Reports

Settings

UCP

## Outbound Routes

### Edit Route

Route Settings

Dial Patterns

Import/Export Patterns

Additional Settings

Route Name ?

sarevoz\_out\_trunk

Route CID ?

Override Extension ?

Yes

No

Route Password ?

Route Type ?

Emergency

Intra-Company

Music On Hold? ?

default

Time Group ?

---Permanent Route---

Route Position ?

---No Change---

Trunk Sequence for Matched Routes ?



Sarevoz\_out



Optional Destination on Congestion ?

Normal Congestion

Note: Extension Routes is not registered

# OUTBOUND ROUTE DIAL PATTERN



Admin

Applications

Connectivity

Dashboard

Reports

Settings

UCP

## Outbound Routes

### Edit Route

Route Settings

Dial Patterns

Import/Export Patterns

Additional Settings

#### Dial Patterns that will use this Route

Pattern Help

[Dial patterns wizards](#)

( prepend )

prefix |

[ [6].

( prepend )

prefix |

[ match pattern

# SIP%.CONF ALWAYS INBOUND TRUNK BEFORE

```
root@localhost:/etc/asterisk
sendrpid=pai
type=peer
context=from-trunk-sip-sarenetCMB_out

[Sarevoz_in]
host=194.30.6.32
username=
secret=
fromuser=
fromdomain=194.30.6.32
sendrpid=no
type=peer
insecure=invite
context=from-trunk-sip-Sarevoz_in
directmedia=no
[Sarevoz_out]
host=194.30.6.32
username=
secret=
fromuser=
fromdomain=194.30.6.32
sendrpid=pai
type=peer
context=from-trunk-sip-Sarevoz_out
directmedia=no
```